SEEPEX SEE POWER EXCHANGE

SEEPEX Client Installation

Version All Versions
February 2016

SEEPEX ad Beograd 412, Vojvode Stepe St.
Belgrade, Serbia

SEEPEX Client Installation

All Versions

Copyright Soops b.v.

All rights reserved. No parts of this work may be reproduced in any form or by any means - graphic, electronic, or mechanical, including photocopying, recording, taping, or information storage and retrieval systems - without the written permission of the publisher.

Products that are referred to in this document may be either trademarks and/or registered trademarks of the respective owners. The publisher and the author make no claim to these trademarks.

While every precaution has been taken in the preparation of this document, the publisher and the author assume no responsibility for errors or omissions, or for damages resulting from the use of information contained in this document or from the use of programs and source code that may accompany it. In no event shall the publisher and the author be liable for any loss of profit or any other commercial damage caused or alleged to have been caused directly or indirectly by this document.

Printed: mei 2016 in Amsterdam

Publisher

Soops b.v.

info@soops.nl

Johan van Hasseltweg 43-2

1021 KN Amsterdam

Phone: +31 (0)20 622 2844

www.soops.nl

Table of Contents

Foreword 0

Chapter I Disclaimer 4

Chapter II ETS Client Installation 6

1 Requirements 7

2 The Install Process 8

Index 15

Copyright Soops b.v.



SEEPEX Client Installation
All Versions

Chapter 1
Disclaimer

Copyright Soops b.v.

Chapter 1 Disclaimer

SEEPEX Trader Client offers a great deal of flexibility to exchanges to configure new products. Considering the generic nature of the SEEPEX Trader Client, and thus this manual, some products and functionality described in this document may not be available to you.

This guide is intended for Traders.

Assumption throughout this guide is made that the reader has full authority and permission to perform the actions required.

Consult the SEEPEX Client Guide for further details about functionality once the installation has completed.

Copyright Soops b.v.



SEEPEX Client Installation
All Versions

Chapter 2
ETS Client Installation

Copyright Soops b.v.

Chapter 2 ETS Client Installation

This guide is intended for SEEPEX Traders.

Please refer to your market rules regarding availability of described functions.

Assumption throughout this guide is made that the reader has full authority and permission to perform the actions required.

There are two different SEEPEX Clients available.

The SEEPEX Fixed Version Client is the full client, containing all program logic needed to perform trader actions. The SEEPEX Fixed Version Client however is not able to update to the latest program logic, making a new manual installation necessary when such code becomes available.

Default installation directory:
C:\Program Files (x86)\ETS Client for SEEPEX (version)

The SEEPEX Upgradable Client is the full client, containing all program logic needed to perform trader actions. The SEEPEX Upgradable Client is able to update to the latest program logic, and will automatically update itself to the latest version when such code becomes available.
This ensures the client software is always up to par without the need to manually collect and install a newer version.

Both the SEEPEX Fixed Version Client and the SEEPEX Upgradable Client will perform identically once the login procedure is completed, given the version of both the clients is the same.

ClientSettings.xml is a local file that contains the basic connection settings needed to connect to the exchange. Each version of SEEPEX Client has its own file. The settingsfile for both Windows 7 and Windows 8 is situated in:

C:\Users\<User>\AppData\Roaming\EPEXTradingSystem\SEEPEX\<version>

The **SEEPEX Trader Client** consists of all functionality needed to perform trading related actions on the SEEPEX Trading Systems installed on your local machine. In order to get up-to-date functionality, manual installation of the latest version is required.

Please note that it is not possible to install both Fixed and Upgradable versions at the same time on the same machine.

Copyright Soops b.v.

2.1 Requirements

Recommended system requirements for the client computer:

Intel Dual Core or equivalent processor,
2048 MB internal memory,
100 Mb of free Hard Disk space.

Supported operating systems:

Windows7 Professional, latest service pack
Windows8, latest service pack
MS Excel 2007, 2010, 2013.
Please note that MS Excel Viewer is not supported.

Network settings:

ETS Trader Client for SEEPEX requires a stable Internet connection.
Recommended minimum connection speed is 256Kbit/s or better.
All traffic is TLS encrypted.

Note:

Using an Upgradable client on Citrix is not recommended.

Copyright Soops b.v.

2.2 The Install Process

Double-click the installation file as received from the exchange.

ETS Client for SEEPEX (version).msi

The installer wizard will now guide you through the installation steps.

In all screens, press **Cancel** to terminate the installation process.
Press **Back** to revert to the previous step in the installation process.

Press **Next**.

Copyright Soops b.v.

The installer wizard now asks for the installation directory.



Optional:
You can change the installation directory with the **Change** button.

Copyright Soops b.v.



Press **OK** when you have selected or entered your installation directory.

Copyright Soops b.v.



You choose for either the fixed or the upgradable client version here.
Check the **checkbox** if you want the client to be upgradable, otherwise leave it unchecked.

Press **Next**.

Copyright Soops b.v.



Press **Install**.

Copyright Soops b.v.

Wait for the installation process to finish.



Press **Finish**.

You can now find your client in the Windows Start menu under **ETS Client for SEEPEX** -> *ETSClient (upgradable)* or *ETSClient* respectively.

Note that also the **uninstall** option can be found here.

Copyright Soops b.v.

Index

- F -

Fixed version 6

- I -

Install 8
Installation directory 6

- R -

Requirements 7

- U -

Uninstall 8
Upgradable version 6

Copyright Soops b.v.